



American Barleywine

Ingredients

6.6 lbs. Amber Liquid Malt Extract _____
6.0 lbs Golden Light Dried Malt Extract _____
Crushed Steeping Grains (in sealed plastic bag): _____

- 1.0 lb. 2-Row Brewers Malt
- 1.0 lb. Munich Malt
- 0.5 lb. Crystal 120
- 2.0 oz. of Roasted Barley

1 Muslin Bag _____
1 Dry Hop Bag _____
3.00 oz Simcoe Hops (1.5oz for dry hopping) _____
3.00 oz Centennial Hops _____
1.00 oz Citra Hops _____
1.00 oz Zythos Hops _____
2 Packages Safale 05 _____
Bottle Caps _____
Priming Sugar _____

American Barleywine Specs:

ABV: 10.30%

IBU's: 99

Original Gravity (OG): 1.099

Final Gravity (FG): 1.022

Color: Rust

Directions

*** Read all recommended procedures and material before you begin to brew.**

*** All equipment must be cleaned and sanitized prior to brewing. It is especially important to clean and sanitize the equipment that comes in contact with your beer after it has been boiled. It must be properly sanitized or you risk affecting the taste and quality of your beer. Please call us if you have any questions or our uncertain about sanitizing. Please make sure your kit contains, malt extract, hops, corn sugar, and yeast before brewing.**

Brewing:

1. Fill your brew pot with 4 gallons of clean water. Heat water to 155 F.
2. Place the steeping grains inside a muslin bag and tie securely. Add the bag to the brew pot for 30 minutes. Maintain 150 F (Do Not Boil). After 30 minutes remove the bag and let drain in to brew kettle (Do not squeeze grain bag). Discard muslin bag with spent grains.
3. Turn off heat and add all of the malt extract. Stir the extract into the water to create your wort. Bring to a gentle boil.
4. **Barleywines require a 90 minute boil. You will boil for half an hour before your first hop addition, so set your timer for 90 minutes.**
5. When your timer says '60 minutes,' add 1.0 oz of Zythos hops to the boiling wort. Do not let the wort boil over your pot. Boil for 30 minutes.
6. Add 1.5 oz of Centennial hops and 1.5 oz of Simcoe hops. Boil for 15 minutes.
7. Add 1.5 oz of Centennial hops and 1.0 oz of Citra hops. Boil for 15 minutes then turn off heat.
8. Cool your boiling pot filled with wort by placing it in your sink filled with cold water. Add ice to the water around the pot to accelerate the cooling process. Also stir the wort periodically with a **sanitized** spoon. When not stirring keep the lid on your brew pot. Replace the water around your pot with cold water when it becomes warm. Continue to cool the wort until it is 80 degrees F. Check the temperature with a **sanitized** thermometer. The wort should take about 20-30 minutes to cool. A copper wort chiller can also be used to cool your wort quicker. Ask us about purchasing one if you would like.



9. Pour your wort into the **sanitized** fermenter. Then add cold water to get up to 5 gallons. Then check the temperature of the wort. Make sure it is 75F or below before you sprinkle (pitch) the yeast on top of the wort. Stir with a **sanitized** spoon or paddle.
10. Place the **sanitized** lid on your fermenter making sure that it is locks securely. **Sanitize your hand or a plastic bag** and cover the hole in the top of the fermenter, and shake or rock your sealed fermenter for 5-10 minutes to aerate the wort. This helps the yeast do it's job.
11. Reopen your fermenter and remove about 8 oz. of wort with a **sanitized** cup or beer thief. Do not touch the wort in the fermenter with your hands. Set the sample aside and replace your lid and airlock filled halfway with sanitizing solution.
12. Place the fermenter in a relatively warm place (65-73 deg F). This is the ideal temperature range for ales to ferment at. You should see evidence of fermentation (bubbling airlock) within 12-36 hours. Not all fermentation behaves the same, and depends on factors such as temperature, yeast strain, and amount of fermentable sugar. Note: Cooler temperatures mean slower fermentation. Do not hesitate to call us or stop by if you have any questions.
13. Now that your fermenter is set aside take the wort sample that you took earlier and pour it into your test jar with the hydrometer in it until it floats. Record the specific (original) gravity and the potential alcohol readings. Discard the wort in the test tube, **do not** put it back into the fermenter.
14. 7 days after brewing transfer your beer to a **sanitized** secondary fermenter (carboy) if you have one, then add 1.5 oz of Simcoe hops for dry hopping. You can use a sanitized hop bag, or just throw them in the fermenter. Leave the dry hops in for 4-7 days. Secondary fermentation is not necessary, but does improve the clarity and flavor of your beer. If you do not have a secondary fermenter then ignore the previous 2 sentences and add the dry hops to your primary fermenter. After 7 days open your fermenter and remove a sample of your beer (8oz) with a sanitized cup or beer thief. Record your specific gravity and potential alcohol readings. Repeat this step every day until your readings stay the same for two days. This ensures that your fermentation is complete. If you are unsure error on the side of caution and wait a few days. Once you are sure that fermentation is complete you can determine the alcohol content of your beer by subtracting the first potential alcohol reading from your final reading (8.0% - 1.5% = 6.5%) Now its time to bottle.

Bottling

1. Clean and sanitize all your bottles. You will need about 48 12oz. bottles or 27 22oz. bottles with non screw off caps. They can be purchased at O'Connor's or saved from your personal drinking stash.
2. Boil about 8oz. of water with your 5oz. of priming sugar for 10 minutes & stir until dissolved. Add this hot solution to your bottling bucket.
3. Siphon your beer from the fermenter to the bottling bucket. Try to leave as much sediment behind on the bottom of the fermenter. Gently stir to mix your sugar solution with your beer.
4. Place your bucket on a table. Remove the hose from the siphon unit, sanitize it then attach it to the spigot on your fermenter. Next attach the bottle bottle filler to the other end of the hose. Open the spigot and allow the beer to fill the hose. Fill each bottle by pressing the bottle filler to the bottom of each bottle. When the beer reaches the top of the bottle pull the bottle filler out of the bottle. When this is done it should leave the correct amount of head space in the bottle.
5. Sanitize your caps by soaking them in your sanitizing solution. To cap place a cap on each bottle and crimp with your capping device. Do not apply too much pressure; just let the capper do the work.
6. Natural carbonation occurs as a result of the suspended yeast in your beer consuming the priming sugar. Allow the beer to carbonate at room temperature (60-70 deg F) for about 10 days before refrigerating. Additional aging will improve the clarity and flavor of your beer. **ENJOY!**